
Problem: The USB Downloader driver is installed, but can not be seen in the QUARTUS software, as shown below:



Answer:

This is a problem of driver installation, You need to uninstall the USB blaster driver and then reinstall it.

First, Open Device Manager, select USB blaster driver, right click to uninstall it, and click Delete button.

Second, reinstall the driver. The path selection is as follows:

A) WIN 7 32-bit system using the driver we provide,

Drive Path: A\06_USB Blaster\USB_Blaster_WIN7 32\CDM 2.04.16 WHQL Certified

B) WIN 7 64 system uses QUARTUS's own driver,

Driver Path select C:\altera\11.0\quartus\drivers